

QUESTIONS & ANSWERS

Kill your exam at first Attempt



DELL-EMC

DES-4122

Specialist - Implementation Engineer PowerEdge Version 2.0

<https://killexams.com/pass4sure/exam-detail/DES-4122>



Question: 14

Which type of access is known as Firmware RACADM on a Dell EMC PowerEdge server?

- A. Accessing RACADM running the Dell Toolkit
- B. Accessing RACADM with OpenManage software
- C. Logging into iDRAC using SSH or Telnet
- D. Logging into iDRAC through Boot Manager

Answer: C

Question: 15

What is the purpose of the Silicon-Based Hardware Root of Trust feature in Dell EMC PowerEdge 14G servers?

- A. Ensures that the installed operating system is authentic
- B. Ensures that the server has a valid Service Tag number
- C. Ensures that no unauthorized BIOS or firmware codes are run
- D. Ensures that the server boots only when connected to a verified network

Answer: C

Question: 16

What are the default settings used when applying firmware and a configuration to a replaced part using the Lifecycle Controller?

- A. Firmware: Upgrade to latest available version
Configuration Apply always
- B. Firmware Allow version upgrade only
Configuration: Disabled
- C. Firmware: Match firmware of replaced part
Configuration Apply always
- D. Firmware Disabled
Configuration Apply only if firmware match

Answer: C

Question: 17

A technician needs to change the iDRAC password on a Dell EMC PowerEdge 14G server in a lights-out datacenter. The be rebooted because it is in production. The iDRAC is configured with the default credentials

How could the technician change the iDRAC password?

- A. SupportAssist Enterprise
- B. iDRAC Web GUI
- C. OpenManage Server Administrator

D. Virtual Console; press F2 after rebooting system

Answer: D

Question: 18

A technician is creating a virtual disk in the iDRAC (2x 4 TB NL-SAS in RAID 1) to install Windows 2016. They manually boot to the OS installation media without using the Lifecycle Controller OS Deployment wizard. Only the first 2048 GB on the virtual disk can be partitioned.

How should the technician obtain access to the remaining 2 TB (approximately) of storage?

- A. Use the Lifecycle Controller OS Deployment Wizard to deploy the OS on this server
- B. Delete the 4 TB virtual disk and create a virtual (boot) disk no larger than 2048 GB
- C. Upgrade to a newer version of the operating system
- D. Use F2 to go into the BIOS, change the BIOS boot mode to UEFI, and try again

Answer: D

Question: 19

A Dell EMC PowerEdge 14G server uses Intel OPTANE DC Persistent Memory in App Direct mode.

What is the minimum size DIMM supported for this type of memory?

- A. 64 GB
- B. 128 GB
- C. 256 GB
- D. 512 GB

Answer: B

Question: 20

A company that has very specific firmware requirements has acquired Dell EMC PowerEdge servers. Any replaced parts of the type must match the original parts identically. The procedure must be as simple as possible with minimal risk.

What action should a technician take to help accomplish this goal?

- A. Configure servers to access the remote firmware repository
- B. Enable the Match Firmware of Replaced Part setting in the system BIOS
- C. Install and configure a repository manager
- D. Enable the Collect System Inventory On Restart (CSIOR) attribute

Answer: B

For More exams visit <https://killexams.com/vendors-exam-list>

